

Appendix 3: Central line-associated bloodstream infection prevention checklist

Public reporting burden of this collection of information is estimated to average 10 minutes per response, including the time for reviewing instructions, searching existing data sources, gathering and maintaining the data needed, and completing and reviewing the collection of information. An agency may not conduct or sponsor, and a person is not required to respond to a collection of information unless it displays a currently valid OMB control number. Send comments regarding this burden estimate or any other aspect of this collection of information including suggestions for reducing this burden to CDC/ATSDR Reports Clearance Officer; 1600 Clifton Road NE, MS D-74 Atlanta, Georgia 30333; ATTN: PRA (0920-1011)

Checklist for Prevention of Central Line Associated Blood Stream Infections

Based on 2011 CDC guideline for prevention of intravascular catheter-associated bloodstream infections:
<http://www.cdc.gov/hicpac/pdf/guidelines/bsi-guidelines-2011.pdf>

For Clinicians:

Promptly remove unnecessary central lines

- Perform daily audits to assess whether each central line is still needed

Follow proper insertion practices

- Perform hand hygiene before insertion
- Adhere to aseptic technique
- Use maximal sterile barrier precautions (i.e., mask, cap, gown, sterile gloves, and sterile full-body drape)
- Perform skin antisepsis with >0.5% chlorhexidine with alcohol
- Choose the best site to minimize infections and mechanical complications
 - Avoid femoral site in adult patients
- Cover the site with sterile gauze or sterile, transparent, semipermeable dressings

Handle and maintain central lines appropriately

- Comply with hand hygiene requirements
- Scrub the access port or hub immediately prior to each use with an appropriate antiseptic (e.g., chlorhexidine, povidone iodine, an iodophor, or 70% alcohol)
- Access catheters only with sterile devices
- Replace dressings that are wet, soiled, or dislodged
- Perform dressing changes under aseptic technique using clean or sterile gloves

For Facilities:

- Empower staff to stop non-emergent insertion if proper procedures are not followed
- "Bundle" supplies (e.g., in a kit) to ensure items are readily available for use
- Provide the checklist above to clinicians, to ensure all insertion practices are followed
- Ensure efficient access to hand hygiene
- Monitor and provide prompt feedback for adherence to hand hygiene
<http://www.cdc.gov/handhygiene/Measurement.html>
- Provide recurring education sessions on central line insertion, handling and maintenance

Supplemental strategies for consideration:

- 2% Chlorhexidine bathing
- Antimicrobial/Antiseptic-impregnated catheters
- Chlorhexidine-impregnated dressings