

## FORM E Soybean Yield Survey Post-Harvest Gleanings 2018



	Da	ite:						
NO	<b>TE:</b> The post-harvest field gleanings should be completed as soon after harvest as possible, and must be done within 3 days after harvest. If the sample field has been plowed, disk pastured since harvest, select an alternate field for gleaning if one is available in the trace.							
FII	ELD OBSERVATIONS	UN	IT 1		UN	IT 2		
1.	Measure distance from plants in Row 1 to plants in Row 2 Feet and Tenths	701			702	·		
2.	Measure distance from plants in Row 1 to plants in Row 5 Feet and Tenths	703			704	·		
GLEANINGS IN 3-FOOT UNITS  CHECK EACH BOX AS COMPLETED								
Put all pods from both units and all whole beans and pieces from both units in the			UNIT 1			UNIT 2		
san	ne paper bag.	ROW 1	ROW 2	г	ROW 1	ROW 2		
3.	Pick all <b>pods</b> with beans attached to plants, and loose pods with beans in each row middle and deposit in a paper bag							
4.	Pick up all <b>whole</b> beans and pieces of beans in each row middle and deposit in the same paper bag used for above item							
5.	Was an alternate field used for making post-harvest observations?							
	☐ <b>YES</b> — (Indicate in Field Notes) ☐ <b>NO</b>							
	<b>FIELD NOTES:</b> If post-harvest observations cannot be made, give reasons here.							
6.	Did a supervisor assist you in working this sample? YES NO							
				-				

ENUMERATOR:	Enumerator Numbe	790
	Supervisor Numbe	791
CHIRDING INCEDITIONS.	·¬	
SHIPPING INSTRUCTIONS:		
Attach completed ID tag to the paper bag(s) containing gleanings.		
Place bag(s) and this Form E in a Tyvek envelope.		
• Ship this Form E to the National Lab in the Tyvek envelope with the gleanings.	ļ	
	- <del></del>	780
	STATUS CODI	E
FORM E: SOYBEANS - continued		
NATIONAL LABORATORY DETERMINATIONS		
NATIONAL LABORATORI DETERMINATIONS		
Date sample received in lab (MM DD)		
Date sample received in lab (why DD)		
Discard any pods with undeveloped beans. Thresh and hull all other pods from bag;		
combine with loose whole beans and pieces of beans.		
F	Γ	71.4
7. Total weight of threshed and loose beans immediately before moisture test	Grams to Hundredths	714
· · · · · · · · · · · · · · · · · · ·	<u> </u>	·— —
8. Moisture content of beans, rounded to tenths 1/	Percent	715
or instance content of sealis, founded to tended the tender that the seal of t	rerent	·—
<sup>1/</sup> If sample weight is too small for moisture test, sufficient beans of known moisture		
content will be added to the sample so that a moisture test can be made. The		
moisture content of the sample can then be derived using the following formula.		
moisture content of the sample can then be derived doing the following formatal		
$(A+B)D-(B\times C)$		
$E = \frac{(A+B)D - (B \times C)}{A}$		
A		
Where A = Weight of small sample (item 7)	. Grams	
1 · ( · · · ) · · · · · · · · · · · · · ·		
B = Weight of additional beans required for moisture test	. Grams	
C = Moisture percent of B	. Percent	
D = Moisture percent of A + B combined	Percent	
E = Result: Moisture percent of small sample (enter in item 8)	Percent	
Lab Technician(s)  Date Analysis O	Completed	
Lab Technician(s) Date Analysis (		104 PP
		MM DD