

# FORM E SOYBEAN YIELD SURVEY - 2026

OMB No.: 0535-0088  
 Approval Expires: x/xx/20xx  
 Project Code: 102  
 Survey ID: 3229



**United States  
 Department of  
 Agriculture**



**NATIONAL  
 AGRICULTURAL  
 STATISTICS  
 SERVICE**

Please make corrections to name, address and ZIP Code, if necessary.

Date: \_\_\_\_\_

**UNIT LOCATION**

1. Number of rows along edge of field.....
2. Number of paces into field.....

UNIT 1	UNIT 2
<b>+ 5</b>	<b>+ 5</b>
<b>+ 5</b>	<b>+ 5</b>

**FIELD OBSERVATIONS**

3. Measure distance from plants in Row 1 to plants in Row 2..... Feet and Tenths
4. Measure distance from plants in Row 1 to plants in Row 5..... Feet and Tenths

UNIT 1	UNIT 2
701 _____	702 _____
703 _____	704 _____

**GLEANINGS IN 3-FOOT UNITS**

*Put all pods from both units and all whole beans and pieces from both units in the same paper bag*

5. Pick all pods with beans attached to plants, and loose pods with beans in each row middle and deposit in a paper bag .....
6. Pick up all whole beans and pieces of beans in each row middle and deposit in the same paper bag used for above item.....
7. Was an alternate field used for making post-harvest observations?

**CHECK EACH BOX AS COMPLETED**

		UNIT 1		UNIT 2	
		ROW 1	ROW 2	ROW 1	ROW 2
Check		<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Check		<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

Yes - (Indicate in Field Notes)       No

FIELD NOTES: If post-harvest observations cannot be made, given reasons here.

---



---

FORM E: SOYBEANS - *continued*

8. Did a supervisor assist you in working this sample?  Yes  No

ENUMERATOR: \_\_\_\_\_

Enumerator Number	790
Supervisor Number	791

**SHIPPING INSTRUCTIONS:**

- Attach completed ID tag to the paper bag(s) containing gleanings.
- Place bag(s) and this Form E in a Tyvek envelope.
- Ship Tyvek envelope to the National Lab.
- Record the UPS Tracking Number on the Kit Envelope.

STATUS CODE	780
-------------	-----

**NATIONAL LABORATORY DETERMINATIONS**

Date sample received in lab (MM DD) \_\_\_\_\_

*Discard any pods with undeveloped beans. Thresh and hull all other pods from bag; combine with loose whole beans and pieces of beans.*

9. Total weight of threshed and loose beans immediately before moisture test..... Grams to Hundredths

714	_____
-----	-------

10. Moisture content of beans, rounded to tenths <sup>1/</sup>..... Percent

715	_____
-----	-------

*<sup>1/</sup>If sample weight is too small for moisture test, sufficient beans of known moisture content will be added to the sample so that a moisture test can be made. The moisture content of the sample can then be derived using the following formula.*

$$E = \frac{(A + B) D - (B \times C)}{A}$$

Where A = Weight of small sample ( <i>item 9</i> ) .....	. ____ ____	Grams
B = Weight of additional beans required for moisture test .....	. ____ ____	Grams
C = Moisture percent of B .....	. ____	Percent
D = Moisture percent of A + B combined .....	. ____	Percent
E = Result: Moisture percent of small sample ( <i>enter in item 10</i> ) .....	. ____	Percent

Lab Technician(s) \_\_\_\_\_ Date Analysis Completed \_\_\_\_\_

MM DD